



SETTING UP OUTLOOK 2007


STEP 1. Open Outlook. Select **Account Settings...** from the **Tools** menu.




STEP 2. On the E-mail tab, click **New**.



STEP 3. Select **Microsoft Exchange, POP3, IMAP or HTTP** and click **Next**



STEP 4. Select "Manually configure server settings or additional server types" and click **Next**



STEP 5. Enter the following information for E-mail Accounts.

Your Name: Enter the name you wish recipients to see when they receive your message.

Email Address: This is the address that your contacts' email program will reply to your messages. This is also the address that will get recorded in your contacts' address book if they add you as a contact.

Account Type: POP3

Incoming mail server: Enter mail.wundersolutions.com

Outgoing mail server (SMTP): Enter mail.wundersolutions.com

User Name: Enter your full e-mail address

Password: If you wish for Outlook to save your password, check the box labeled **Remember Password** and enter your password in the text field.

Click **More Settings...**

Change E-mail Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information

Your Name: John Doe

E-mail Address: johndoe@yourdomain.com

Server Information

Account Type: POP3

Incoming mail server: mail.wundersolutions.com

Outgoing mail server (SMTP): mail.wundersolutions.com

Logon Information

User Name: johndoe@yourdomain.com

Password: *****

Remember password

Require logon using Secure Password Authentication (SPA)

Test Account Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings ...


More Settings ...

< Back Next > Cancel

STEP 6.

Verify these tabs are correct.

Click on the **Outgoing Server** tab, and check the box labeled **My outgoing server (SMTP) requires authentication**. Then choose to **Use same settings as my incoming mail server**



Click on the **Advanced** tab.

- Under **Incoming Server (POP3)**, the port number should be set to **993**. CHECK the **SSL** box
- Under **Outgoing Server (SMTP)**, the port number should be set to **465**.

Click **OK**

